

Kelvin Designs Presets - Quick Start Tutorial

Sometime the zip function doesn't work well with windows, and most of the time this has been solved by installing this free software to unzip the files <http://www.7-zip.org/>.

Installing Lightroom Presets

1. Unzip the files, and select the folder containing the presets ("PhotoSerge-Vol..."). Right click and choose "Copy PhotoSerge..."
2. Open Lightroom, and go into Preferences -> Presets Tab.
3. Click on "Show Lightroom Presets Folder..."
4. Locate and open the "Develop Presets" folder and paste the new folder in that folder.
5. Restart Lightroom and the presets will appear in the develop module as "PhotoSerge-Vol..."

Installing Photoshop Presets in Mac

1. Open the folder "Photoshop Presets" that you downloaded and un-zipped. Select all the ".xmp" files and copy (Command-C).
2. Go to the Finder and open a new window (Command-N).
3. Go to the "Go" Menu at the top, hold down "Alt" or "Option" and the "Library" sub-menu should appear. Click on this.
4. Go to "Application Support" -> "Adobe" -> "Camera Raw" -> "Settings".
5. In the Settings folder, paste the ".xmp" files you had earlier copied (Command-V).

Installing Photoshop Presets in Windows

1. Open up "My Computer".

Navigate to your C drive.

FOR WINDOWS 7

2. Go to the folder Users > YOUR USER NAME > AppData > Roaming > Adobe > CameraRaw > Settings
3. If you cannot see the "AppData" folder, do the following:
 - a. Open Folder Options by clicking the Start button Picture of the Start button, clicking Control Panel, clicking Appearance and Personalization, and then clicking Folder Options.
 - b. Click the View tab.
 - c. Under Advanced settings, click Show hidden files, folders, and drives, and then click OK.

FOR WINDOWS XP

2. Go to the folder Documents and Settings > YOUR USER NAME > ApplicationData > Roaming > Adobe > CameraRaw > Settings
3. If you cannot see the "Application Data" folder do the following:
 - a. Open Folder Options in Control Panel.
 - b. Click Start, and then click Control Panel.
 - c. Click Appearance and Themes, and then click Folder Options.
 - d. On the View tab, under Hidden files and folders, click Show hidden files and folders.
4. Copy the contents of the "Photoshop Presets" folder into this folder.